



# E20-598<sup>Q&As</sup>

Backup and Recovery - Avamar Specialist Exam for Storage Administrators

## Pass EMC E20-598 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.passapply.com/e20-598.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by EMC  
Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers





### QUESTION 1

Which tool is used to move a client to a new domain in EMC Avamar 6.0?

- A. Client Manager
- B. Activation Manager
- C. Enterprise Manager
- D. Installation Manager

Correct Answer: A

## Clients page

Avamar Client Manager's **Clients** page provides information and tools for working with Avamar clients.

From the **Clients** page you can:

- ◆ Select the computers in your enterprise's domain and add them as Avamar clients
- ◆ View detailed information about individual clients
- ◆ Move, retire, and delete clients
- ◆ Change a client's group associations
- ◆ Upgrade the Avamar software on the client

To navigate between the sections of the Clients page, select from the choices in the left-side menu.

---

### QUESTION 2

What is the physical memory requirement for an EMC AVE with 1 TB capacity?

- A. 6 GB
- B. 8 GB
- C. 16 GB
- D. 32 GB

Correct Answer: B

AVE 7



**Table 3** Minimum requirements for AVE

	0.5 TB AVE	1 TB AVE	2TB AVE	4 TB AVE
Processors	Minimum two 2 GHz processors	Minimum two 2 GHz processors	Minimum two 2 GHz processors	Minimum four 2 GHz processors
Memory	6 GB	8 GB	16 GB	36 GB
Disk space	850 GB	1,600 GB	3,100 GB	6,100 GB
Network connection	1 GbE connection	1 GbE connection	1 GbE connection	1 GbE connection

AVE 6

**Table 3** Minimum requirements for AVE

	0.5 TB AVE	1 TB AVE	2 TB AVE
Processors dedicated to AVE	Minimum two 2 GHz processors available to AVE at all times	Minimum two 2 GHz processors available to AVE at all times	Minimum two 2 GHz processors available to AVE at all times
Physical memory dedicated to AVE	6 GB	8 GB	16 GB
Disk space	850 GB	1,600 GB	3,100 GB
Network connection	1 GbE connection	1 GbE connection	1 GbE connection

**QUESTION 3**

You are working in a Microsoft Windows Active/Passive cluster environment. On which cluster node(s) must the EMC Avamar Windows file system client be installed?

- A. Active and passive clients only
- B. Active client only
- C. Virtual client only
- D. Active, passive, and virtual clients

Correct Answer: A



#### QUESTION 4

What are members of an EMC Avamar group policy?

- A. Notification, Retention, Schedule
- B. Notification, Profile, Dataset
- C. Clients, Profile, Retention
- D. Dataset, Schedule, Retention

Correct Answer: D

---

#### QUESTION 5

What is used to transfer configuration files to the EMC Avamar switch?

- A. TFTP
- B. SFTP
- C. FTP
- D. SCP

Correct Answer: A

[Latest E20-598 Dumps](#)

[E20-598 PDF Dumps](#)

[E20-598 Practice Test](#)