



# AZ-801<sup>Q&As</sup>

Configuring Windows Server Hybrid Advanced Services

## Pass Microsoft AZ-801 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.passapply.com/az-801.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by Microsoft  
Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers





### QUESTION 1

You have an on-premises network and an Azure virtual network.

You establish a Site-to-Site VPN connection from the on-premises network to the Azure virtual network, but the connection frequently disconnects.

You need to debug the IPsec tunnel from Azure.

Which Azure VPN Gateway diagnostic log should you review?

- A. GatewayDiagnosticLog
- B. RouteDiagnosticLog
- C. IKEDiagnosticLog
- D. TunnelDiagnosticLog

Correct Answer: D

Reference: <https://docs.microsoft.com/en-us/azure/vpn-gateway/troubleshoot-vpn-with-azure-diagnostics>

---

### QUESTION 2

You have an Azure virtual machine named VM1.

You install an application on VM1, and then restart the virtual machine.

After the restart, you get the following error message: "Boot failure. Reboot and Select proper Boot Device or Insert Boot Media in selected Boot Device."

You need to mount the operating system disk offline from VM1 to a temporary virtual machine to troubleshoot the issue.

Which command should you run in Azure CLI?

- A. az vm repair create
- B. az vm boot-diagnostics enable
- C. az vm capture
- D. az vm disk attach

Correct Answer: A

Reference: <https://docs.microsoft.com/en-us/cli/azure/vm/repair?view=azure-cli-latest>

---

### QUESTION 3

HOTSPOT



What is the effective minimum password length for User1 and Admin1? To answer, select the appropriate options in the answer area.

NOTE: Each correct selection is worth one point.

Hot Area:

## Answer Area

User1:

	▼
8	
9	
10	
11	
12	

Admin1:

	▼
8	
9	
10	
11	
12	

Correct Answer:



# Answer Area

User1:

	▼
8	
9	
10	
11	
12	

Admin1:

	▼
8	
9	
10	
11	
12	

Explanation:

Box 1: 9

When multiple PSOs apply to a user, the PSO with the highest precedence (lowest precedence number) applies which in this case is PSO1.

Box 2: 8

There are no PSOs applied to Admin1 so the password policy from the Default Domain GPO applies.

The Minimum password length setting in GPO1 would only apply to local user accounts on computers in OU1. It does not apply to domain user accounts.



**QUESTION 4**

**HOTSPOT**

You have three servers named Host1, Host2, and VM1 that run Windows Server. Host1 and Host2 have the Hyper-V server role installed. VM1 is a virtual machine hosted on Host1.

You configure VM1 to replicate to Host2 by using Hyper-V Replica.

Which types of failovers can you perform on VM1 on each host? To answer, select the appropriate options in the answer area.

NOTE: Each correct selection is worth one point.

Hot Area:

**Answer Area**

VM1 on Host1:

	▼
Failover only	
Test Failover only	
Planned Failover only	
Failover and Planned Failover only	
Test Failover and Failover only	

VM1 on Host2:

	▼
Failover only	
Test Failover only	
Planned Failover only	
Failover and Planned Failover only	
Test Failover and Failover only	

Correct Answer:



## Answer Area

VM1 on Host1:

	▼
Failover only	
Test Failover only	
Planned Failover only	
Failover and Planned Failover only	
Test Failover and Failover only	

VM1 on Host2:

	▼
Failover only	
Test Failover only	
Planned Failover only	
Failover and Planned Failover only	
Test Failover and Failover only	

### QUESTION 5

Your company uses Storage Spaces Direct.

You need to view the available storage in a Storage Space Direct storage pool.

What should you use?

- A. System Configuration
- B. File Server Resource Manager (FSRM)
- C. the Get-StorageFileServer cmdlet
- D. Failover Cluster Manager

Correct Answer: D

If Failover Cluster Manager, select the Storage Space Direct storage pool. The information displayed in the main window includes the free space and used space.